



RockWare®

Earth Science Software, Consulting & Training

Quick Start – PetraSim – Network License – User Info

Server Setup _____

The network version requires installation of a license manager administrator program which is installed separately. We will email information about the license manager to the designated contact on your account.

Installing PetraSim _____

You must have Administrator privileges to install and license PetraSim. The PetraSim program should be installed on to each client computer.

1. Visit www.rockware.com and click on the [Downloads / Product Updates / PetraSim](#).
2. Scroll down to the most current version of PetraSim available to you based on your Maintenance Expiration Date and click the **Download** link.
3. **Save** the installation program to your computer.
4. When the download is complete, **double-click** on the installation file to start the installation. Follow the recommended installation settings.

Licensing PetraSim _____

1. When installation is complete, start the program. In the main PetraSim window click the Registrar button, and the PetraSim License window will be displayed.
2. In the PetraSim licensing window:
 - a. **License Type:** On the left side of the window choose **Network**.
 - b. Enter the licensing information. This is typically supplied by your network administrator.
 - **Host:** Enter the name or IP address of the server where the RockWare Network Licensing Service has been installed and is running. If the end user is currently connected to that server, you can also try the **Listen for a Server** option.
 - **Port:** Type into this prompt the port number that the Licensing Service is using. This will default to 5280 but may have been changed by the network administrator when the Licensing Service was installed and set up.
 - **Protocol:** Select which IP Protocol is being used – version 4 or version 6.
3. Click the **Connect** button to proceed in to the program. If the licensing was successful, you will see the status in PetraSim licensing windows.
4. **Borrowing a seat:** If your network administrator has activated this feature, you may borrow a license for use on your computer when you are not connected to the network. Simply click the **Borrow a License** button in the PetraSim licensing screen. Set the date on which the temporary local license will expire, and click OK. PetraSim will then operate as a stand-alone license for this time period. When you return to the office, start PetraSim, select **Help / Change Licensing**, and click the **Return License** button to check in your borrowed seat.

Getting Help _____

- Run through the **Tutorial** lessons: Click the **Help / Online Help** to find the PetraSim and simulator manuals, tutorials and example problems.
- Join the online **support forum** where user post questions and answers: Visit www.rockware.com, click **Support / Support Forum**.
- Contact our **technical support staff** at tech@rockware.com.